MetaModule 101

```
112
$any2mobile;                                    114
        {http://www.any2mobile.com/home.html;
                {
                        Submit name="login" _userid=jdoe _password=test!
110 ——          117 —— tanc Welcome!
                        text!
                        wav aany2mobile!

                        ranc!
                118 —— ranc Horoscope &ChannelTitle!
                        sos 1!
                        mask Horoscope!

                        ranc!
                119 —— ranc &ChannelTitle Sports!
                        sos 1!
                        mask Sports!
140
    Horoscope;
            {//;    142
                {       ranc!
                        ranc &TitleClass Horoscope !
                        Metrow &TitleClass !
                        Replace "Capricorn" @capricorn.wav "Aquarius"
                                @aquarius.wav "Pisces" @pisces.wav "Virgo"
                        148 ———— @virgo.wav "Aries" @aries.wav "Sagitarius"
                                @sagittarius.wav "Scorpio" @scorpio.wav "Cancer"
                                @cancer.wav "Leo" @leo.wav "Libra" @libra.wav
                                "Gemini" @gemini.wav "Taurus" @taurus.wav!  text!
    *                   \hmodify

150
    Sports;
            {//;
                {       ranc!
                        ranc &TitleClass Sports!
                        Metrow channelTitle!text!

                }
```

Fig. 1

US 7,509,671 B1



Fig. 2

US 2005/0240408 A1


USERS
307
PHONE SERVER 310
TELEPHONY HARDWARE 312
PHONE SERVER APPLICATION 311
SPEECH RECOGNITION ENGINES 314
TEXT-TO-SPEECH 316
TELEPHONE API 318
TELEPHONE FRAMEWORK API 318
USER PROFILES 342
SITE PROFILES 344
METABROWSER 350
METAMODULES REPOSITORY 340
INTERNET 302
380
SITE 381
SITE 383
SITES 384
METAMODULES REPOSITORY 385

FIG. 3


EXECUTE METAMODULES
ESTABLISH CALL SESSION FOR USER
410
SELECT INITIAL METAMODULE FOR THE USER
414
LOAD CURRENT METAFILE
416
C
ACTIVATE PRESETS (SO THAT THEY MAY BE INVOKED BY VOICE COMMANDS) OF CURRENT METAFILE
420
EXECUTE ENTRY PRESET OF CURRENT METAFILE
424
B
WAIT FOR USER COMMAND
430
RECEIVE USER COMMAND (E.G. VOICE COMMAND)
434
A

Fig. 4


A
550
DID USER COMMAND INVOKE AN ACTIVE PRESET?
NO
570
IS THE USER COMMAND A LINGO COMMAND?
YES
574
EXECUTE LINGO COMMAND
YES
554
IS CURRENT PRESET LINK TO ANOTHER METAMODULE?
YES
556
LOAD OTHER METAMODULE
C
NO
EXECUTE CURRENT PRESET
558
562
IS THE CURRENT PRESET AN EXIT PRESET?
Yes
564
DEACTIVATE SUBMENU
NO
B

Fig. 5


EXECUTE PRESET
610
DOES PRESET SPECIFY A DIFFERENT CURRENT PAGE?
YES
614
LOAD PAGE
618
ESTABLISH AS CURRENT PAGE
NO
620
IS THERE A NEXT INSTRUCTION IN INSTRUCTION LIST?
EXIT
NO
YES
624
EXECUTE NEXT INSTRUCTION

Fig. 6

T09Th0" 2T0h5260



FIG. 7

T09T-hO" 2T0h5260



FIG. 8

T09TH0" 2T0H5260

FIG. 9